



Thank you

for downloading this pdf file from Knitting-and.com!

Your visits have helped keep Knitting-and.com online, providing free crafts and recipes since 1996.

There are hundreds of free patterns and crafts available and more added all the time!

Note: The pink watermark on the following pages will not show if you print this file.



<https://www.knitting-and.com>

A

ABBREVIATIONS:—K. = Knit plain; P. = Purl; tog. = together; wl. fwd. = wool forward; p.s.s.o. = pass slip stitch over; w.o.n. = wool over needle; w.r.n. = wool round needle; t.b.l. = through the back of the loops; ch. = chain; tr. = treble; s.c. = single crochet; d.c. = double crochet; l.tr. = long treble (wool over hook twice); sl. st. = slip stitch; sp. = space.

IMPORTANT!

The correct size of any of the garments illustrated in this Book will only be obtained by USING THE WOOL RECOMMENDED IN THE RECIPE AND KNITTING AT THE CORRECT TENSION. To ensure this, use the wool and needles specified, and knit a small piece of fabric in the given pattern. If knitted correctly, the number of stitches to the inch in width should correspond with the tension given.

¶ When the instructions read, "Cast off 2 stitches, K.2" (or similar stitches), the stitch on the right-hand needle, after casting off, is counted as one stitch.

TEA COSY (Fig. A)— "Lorne" Design.



● *Illustrated on Back Cover.*

MATERIALS:—

PATON'S "ZINNIA" Knitting Wool

or

PATON'S "TOTEM" Knitting Wool.

"Zinnia"—Rose (shade 2025) 5 ozs.

A No. 7 "Inox" Crochet Hook.

ABBREVIATIONS:—See page 3.

TENSION:—

It is absolutely necessary to work at a tension to produce 1 tr. to $\frac{5}{8}$ inch in height and 4 tr. to 1 inch in width.

FIRST HALF.—Commencing at top, make 57 ch., turn.

1st row.—Miss 2 ch., 55 d.c. in 55 ch., turn.

2nd row.—3 ch., 55 tr. on 55 d.c., turn.

3rd row.—3 ch., 1 tr. round front of 1 tr., * 4 tr. round back of 4 tr., 4 tr. round front of 4 tr., repeat from * five times, 4 tr. round back of 4 tr., 2 tr. round front of 2 tr., turn.

4th row.—3 ch., 1 tr. round back of 1 tr., * 4 tr. round front of 4 tr., 4 tr. round back of 4 tr., repeat from * five times, 4 tr. round front of 4 tr., 2 tr. round back of 2 tr., turn.

Repeat the 3rd and 4th rows seven times, then the 3rd row once (work this row firmly). Fasten off.

Work the Second Half in the same manner.

Sew up the seams for 2 inches, leaving a space of $3\frac{1}{2}$ inches for the spout and handle.

Sew up the remainder of the seams. Run a thread through the commencing chain, draw up to 11 inches, and fasten off. Sew together the top of each piece of the Cosy. Using 6 strands of wool, 50 inches long, make a twisted cord. Sew along the top of the Cosy, making three loops in the centre.